



PowerBeam M5

airOS

MAIN WIRELESS NETWORK ADVANCED SERVICES SYSTEM Tools: Logout

Basic Wireless Settings

Wireless Mode: Station

WDS (Transparent Bridge Mode): ☒ Enable

SSID: /\_wifi\_bridge Select...

Lock to AP: 80:2A:A8:38:28:B4

Country Code: Russia Change...

IEEE 802.11 Mode: A/N mixed

DFS: ☐ Enable

Channel Width: 30 MHz

Frequency Scan List, MHz: ☒ Enable 5765 Edit...

Calculate ERP Limit: ☒ Enable

Antenna: 400 - 25 dBi

Output Power: 3 dBm

Data Rate Module: Default

Max TX Rate, Mbps: MCS 7 - 97.5/108.3 ☒ Auto

Wireless Security

Security: WPA2-AES

WPA Authentication: PSK

WPA Preshared Key: Show

Change

GENUINE PRODUCT

© Copyright 2006-2015 Ubiquiti Networks, Inc.

PowerBeam M5

airOS

MAIN WIRELESS NETWORK ADVANCED SERVICES SYSTEM Tools: Logout

Network Role

Network Mode: Bridge

Disable Network: None

Configuration Mode

Configuration Mode: Simple

Management Network Settings

Management IP Address: ☐ DHCP ☒ Static

IP Address: 1

Netmask: 255.255.255.0

Gateway IP: 1

Primary DNS IP: 1

Secondary DNS IP: 1

MTU: 1500

Management VLAN: ☐ Enable

Auto IP Aliasing: ☒ Enable

STP: ☐ Enable

IPv6: ☐ Enable

Change

GENUINE PRODUCT

© Copyright 2006-2015 Ubiquiti Networks, Inc.

PowerBeam M5
air OS

MAIN
WIRELESS
NETWORK
ADVANCED
SERVICES
SYSTEM
Tools:
Logout

### Advanced Wireless Settings

RTS Threshold: 2346 Off

Distance: 0.9 miles (1.4 km) Auto Adjust

Aggregation: 32 Frames 50000 Bytes Enable

Multicast Data: Allow

Installer ERP Control: Enable

Extra Reporting: Enable

Sensitivity Threshold, dBm: -96 Off

### Advanced Ethernet Settings

LAN0 Speed: 100Mbps-Full

### Signal LED Thresholds

	LED1	LED2	LED3	LED4
Thresholds, dBm:	-94	-80	-73	-65

Change

© Copyright 2006-2015 Ubiquiti Networks, Inc.

PowerBeam M5
air OS

MAIN
WIRELESS
NETWORK
ADVANCED
SERVICES
SYSTEM
Tools:
Logout

### Ping Watchdog

Ping Watchdog: Enable

IP Address To Ping:

Ping Interval: 300 seconds

Startup Delay: 300 seconds

Failure Count To Reboot: 3

Save Support Info:

### SNMP Agent

SNMP Agent: Enable

SNMP Community: public

Contact:

Location:

### Web Server

Web Server: Enable

Secure Connection (HTTPS): Enable

Secure Server Port: 443

Server Port: 80

Session Timeout: 15 minutes

### SSH Server

SSH Server: Enable

Server Port: 22

Password Authentication: Enable

Authorized Keys: Edit...

### Telnet Server

Telnet Server: Enable

Server Port: 23

### NTP Client

NTP Client: Enable

NTP Server: 0.ubnt.pool.ntp.org

### Dynamic DNS

Dynamic DNS: Enable

Service: dyndns.org

Host Name:

User Name:

Password: Show

### System Log

System Log: Enable

Remote Log: Enable

Remote Log IP Address:

Remote Log Port: 514

TCP Protocol: Enable

### Device Discovery

Discovery: Enable

CDP: Enable

Change

PowerBeam M5
air OS

MAIN
WIRELESS
NETWORK
ADVANCED
SERVICES
SYSTEM
Tools:
Logout

### Firmware Update

Firmware Version: XW.v5.6.2

Build Number: 27929

Check for Updates: Enable Check Now

Upload Firmware: Обзор... Файл не выбран.

### Device

Device Name: MP\_Server

Interface Language: English

### Date Settings

Time Zone: (GMT+05:00) Ekaterint

Startup Date: Enable

Startup Date:

### System Accounts

Administrator User Name: ubnt

Read-Only Account: Enable

### Miscellaneous

Reset Button: Enable

### Location

Latitude:

Longitude:

Change

### Device Maintenance

Reboot Device: Reboot...

Support Info: Download...

### Configuration Management

Back Up Configuration: Download...

Upload Configuration: Обзор... Файл не выбран.

Reset to Factory Defaults: Reset...

© Copyright 2006-2015 Ubiquiti Networks, Inc.